

DART

Automatic camera configuration

Pau Cano Ribé



Document Changes

1.1	28/10/2020	Added Table of Contents, figure numeration, Document Changes Table. Small format changes
-----	------------	--

Table of Contents

1. Introduction..... 1

2. Usage 2

3. Requirements 2

1. Introduction

When a new Simulation is created in DART, the cameras are configured with a single band, which corresponds to the green peak in the visible spectrum.




Fig. 1.1: Default spectral band in DART and its corresponding settings.

Setting complex cameras is a slow and repetitive work, and as such, can be automated.

The `band_setting.py` python script uses a .txt file where sensors are described by their central wavelength and their spectral bandwidth, setting the DART spectral band files to match the sensors. 3 text files are included with the script, showing 3 different types of cameras:

- `dart_camera_RGB.txt`: simple RGB camera, with 3 spectral bands
- `dart_camera_sequoia.txt`: Sequoia-like camera, with 5 spectral bands
- `dart_camera_sentinel_2.txt`: Sentinel-2 camera, with 13 spectral bands

The contents of the file `dart_camera_sentinel_2.txt` are shown here, as an example of how the file should be. The first column sets the central wavelength of the camera band. The second column, optional and separated by a space, sets the bandwidth of that band. If no there's no second column, the bandwidth will be set to 0.

```
0.443 0.02
0.49 0.065
0.56 0.035
0.665 0.03
0.705 0.015
0.74 0.015
0.783 0.02
0.842 0.115
0.865 0.02
0.945 0.02
1.375 0.03
1.61 0.09
2.190 0.180
```

2. Usage

The script modifies an XML file that stores all the bands of the camera, and their settings. This XML file can be found at Input/phase.xml in the main folder of the simulation.

The script needs 2 parameters to work:

- -f pathToFolder: path to the simulation folder
- -i cameraData.txt: path to the text file with camera settings

It can also use 2 optional parameters:

- -o outputXML: path to the output XML file. When not used, the original XML file is overwritten.
- -d: do not delete old camera settings from the file. If enabled, bands will be added to the file, instead of overwritten.

As such, general execution of the script would be:

```
python band_setting.py -f simulationFolder -i input.txt [-o output.xml -d]
```

And with an example:

```
python band_setting.py -f C:\Users\user\ Dart\user_data\simulations\testSimulation -i  
C:\Users\user\ Dart\user_data\dart_camera_RGB.txt
```

3. Requirements

Python is required to be installed for the script to work.